

# EA SPORTS™ MADDEN NFL™ SEASON 2

## Software Restore Guide



Follow the instructions below if you need to re-install the EA SPORTS™ MADDEN NFL™ SEASON 2 software on your cabinet. **Total installation time is about 30 minutes.**

**Important:** When you use the System Recovery Disk, you will erase all game settings, exhibition leaderboards, and coin and game audits. It is advisable to contact Technical Support before using the System Recovery Disk to resolve a problem.

### System Recovery Disk

Restoring the operating system with the System Recovery Disk takes about 10-15 minutes.

1. With the cabinet powered ON, open the CD drive and insert the CD labeled **System Recovery Disk**. Power the cabinet OFF and then ON. The computer will reboot from the CD. You will see a series of screens on the monitor.
2. After about 5 minutes, you will be prompted to remove the CD and turn the cabinet OFF and then ON. (**Do not** insert the Game Software CD yet!)
3. When the computer reboots, you may see a blank screen for 10-15 seconds, followed by a series of processing screens. After a few minutes the system will reboot, and you will be prompted to insert Game Disk 1. Proceed to install the Game Software CDs as described below.

### Game Software CDs

Game software installation takes about 15-25 minutes.

1. Open the CD drive and insert the CD labeled **Game Install Disk 1 of 2**. The computer will read the CD automatically (do not reboot). You will see a series of screens.  
**Note:** If nothing happens, make sure that you inserted the correct disk.
2. After about 10 minutes you will be prompted to insert Disk 2. Open the CD drive and insert the CD labeled **Game Install Disk 2 of 2**. The computer will read the CD automatically (do not reboot). You will see another series of screens and then the system will reboot.
3. After the system reboots and the game starts, remove the disk from the CD drive.
4. Press the Operator button to start the Operator Menus and set up your game.
5. Play a game to verify proper operation.
6. Register your cabinet, or select **Restore** from the Operator Menu Registration screen to restore your previous cabinet registration.

040-0043-01 Rev. C 7/25/2006 © 2006 GLOBAL VR